

Installing the Driver for Windows XP (6 pages)

A. Download and Extract New Driver (if you are using the Driver disc skip to part B)

1. Download the new driver.
2. Open the AnaPrint V3 .2.zip file and copy the **inf** folder to the desktop.
3. Now you are ready to install the driver.

B. AnaPrint Driver Disc


1. Insert the AnaPrint driver disc (skip if you have already downloaded the driver)
2. From the driver disc click on the **Driver** heading/folder
3. Access the English language folder (if that is the language that is desired) and copy the **inf** folder to the desktop.
4. Now you are ready to install the driver.

C. Installing New Driver


1. Unplug USB cable from Printer side OR PC side
2. Re-plug in USB cable
3. Found New Hardware Wizard will appear. For the first screen, choose "No, not this time" then click Next



4. Choose "Install from a list or specific location (Advanced)" then click Next



5. Choose "Don't search. I will choose the driver to install." then click Next




6. Click on Have Disk




7. Click on Browse



8. Browse to the Desktop, then double click on the folder "INF"



9. Double click on "adacolor.inf"



10. Click on OK



11. Click on Next



12. When prompted, click on Continue Anyway



13. Click on Finish



14. Your new AnaJet driver is now installed.